

MANUAL BLONG MEKEM PLANTE SUT BLONG BANANA AOT LONG WAN STAMPA

**Blong Adapt long
Climate Change long Vanuatu**



Vanuatu Department of Agriculture and Rural Development (DARD) &
SPC-GIZ Coping with Climate Change in the Pacific Island Region (CCCP-IR)

Funding sources: Federal Republic of Germany through the Federal Ministry for
Economic Cooperation and Development (BMZ)

Regional partners: SPC, SPREP and USP



giz



Hao Bae Banana Teknik ia Help blong Adapt long Climate Change?

Climate jenj I stap afektem Vanuatu bigwan naoia. Ol jenj long ren mo tempaja I save spoilem agrikalja. Climate change tu I stap bringim ol strongfala win olsem tropical cyclone we I stap daonem plante crops blong yumi.

Gavmen blong Vanuatu I stap traem faenem ol wei blong helpem ol fama blong oli save laef wetem ol jenj ia. Long akrikalja I kat plante samting we ol fama oli save mekem blong adapt long acclimate change.

Banana hemi wan crop long Vanuatu we hemi isi blong cyclone I daonem. Afta long cyclone samfala taem I had blong faenem planting material blong yu save planem bak plantesen blong yu.

Blong solvem problem ia, DARD mo GIZ I kam ap wetem wan niufala teknik blong mekem se yu save kat plante sut blong banana aot long wan stampa nomo.

Ol Materials blong Mekem Grafting/Maretem Aranis

- > Smol Sharp Naef
- > Han Glav o Klin Hans
- > Klin Tebol
- > Smolsmol Sodast
- > Empty 200L Dram Mazut



Hao blo Mekem Banana Multiplikesen:

A. Buildem wan gudfala nursery blong putum banana long hem. Yu save usum grin net, platic, o plastic kapa blong blokem san I no strong tumas. Mek sua se ol materials oli klin.



B. Priperem dram blong usum insaed long nerseri. Katem dram I ko long tufala haf. Dram hemi mas klin gud blong no spoilem banana. Sapos hemi wan olfala dram, yu save pentem I waet. Yu mas putum plante smolsmol hol insaed long insaed long dram blong mekem se wota I no save fulap long hem.



C. Karem wan yang sut blong banana we yu wantem multiplae long hem. Bae yu lukim se I stret sapos ol leaves blong hem oli shut yet. Sapos yu karem wan olfala banana we I bigwan finis, bae I isi blong hemi ded wetem teknik ia. Be ol yang banana oli save kro gud fromwe hemi fresh mo kat strong energy iet blong kro.



D. Afta yu jusum banana blong yu multiplaem, mas wasem gud blong I no kat eni graon long stampa o long rus blong hem. Bifo u mekem teknik ia yu mas putum I stap drae 1 ful dei long wan klin ples (bae I no stap sitdaon lo graon).



E. Redi long wan gudfala klin tebol blong statem teknik ia.



F. Katem out ol skin raon long stampa blong banana mo katem aot evri rus blong banana. Sapos yu luk eni ples we I stink, yu mas katem aot blong raon stampa hemi klin gud.



G. Katem aot ol difren layers blong skin blong banana, raonem stampa wetem naef plante taem blong katem aot ol skin. Bae yu lukim se hemi olsem ol stairs I ko antap.

H. Sapos yu redi blong katem aot skin raon long stampa, statem naef blong yu long ples we tufala skin I stap mit. Bae yu lukim se hemi mekem wan leta V shape. Be yu no mas kat stret long leta V ples, bae yu kat I ko antap smol, 2mm olsem.

I. Bae yu save katem aot skin koko kasem taem we yu nomo luk leta V. Bae yu lukim se hemi wan pis skin nomo nao.

J. Afta we evri skin I kam aot, bae yu nid blong katem aot haf stampa we I stap iet. Be no katem I ko daon tumas. Bae yu katem inaf nomo blong I save ko insaed long dram blong sodast.



K. Nao leko stampa I stap spel long 48 hrs (2 deis) we yu nomo katem eni samting.

L. Afta long spel ia, bae yu save lukim gud main sut blong banana long medel blong stampa. Blong mekem se banana I save kat fulap smolsmol sut, yu mas stikim main sut I ded wetem naef blong yu.

M. Blong kilim main sut, putum naef antap stret lo ples we I stap grow long hem. Prestem naef I ko down kasem yu nomo lukim back blong knife (3-5cm nomo). Katem main sut long wan kros shape o star shape.

N. Nao yu save putum stampa blong banana insaed long dram wetem smolsmol sodast. Yu sud berem be I no dip tumas. No givim eni wota long fes 48 hours, be afta long taem ia, givim plante wota long stampa insaed long drum



O. Afta lo 8-15 dei bae yu stat blong lukim ol fesfala sut oli stap kamaot long saed saed blong stampa.

P. Taem yu lukim se ol sut oli enaf blong planem, yu save stat blong latem aot wan wan sut mo putum long poly-bak. Aot long wan stampa banana yu save karem kasem 50 sut.



SPC/GIZ Coping with Climate Change
in the Pacific Island Region (CCCPIR)

PO Box 306, Port Vila, Vanuatu

Phone: +678 555 2187 / 29594 & E-Mail: Christopher.Bartlett@giz.de

giz

